

Internet Engineering Task Force (IETF)  
Request for Comments: 6475  
Category: Standards Track  
ISSN: 2070-1721

G. Keeni  
Cyber Solutions, Inc.  
K. Koide  
KDDI Corporation  
S. Gundavelli  
Cisco  
R. Wakikawa  
Toyota ITC  
May 2012

## Proxy Mobile IPv6 Management Information Base

### Abstract

This memo defines a portion of the Proxy Mobile IPv6 Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, the Proxy Mobile IPv6 MIB can be used to monitor and control the mobile access gateway (MAG) and the local mobility anchor (LMA) functions of a Proxy Mobile IPv6 (PMIPv6) entity.

### Status of This Memo

This is an Internet Standards Track document.

This document is a product of the Internet Engineering Task Force (IETF). It represents the consensus of the IETF community. It has received public review and has been approved for publication by the Internet Engineering Steering Group (IESG). Further information on Internet Standards is available in Section 2 of RFC 5741.

Information about the current status of this document, any errata, and how to provide feedback on it may be obtained at <http://www.rfc-editor.org/info/rfc6475>.

## Copyright Notice

Copyright (c) 2012 IETF Trust and the persons identified as the document authors. All rights reserved.

This document is subject to BCP 78 and the IETF Trust's Legal Provisions Relating to IETF Documents (<http://trustee.ietf.org/license-info>) in effect on the date of publication of this document. Please review these documents carefully, as they describe your rights and restrictions with respect to this document. Code Components extracted from this document must include Simplified BSD License text as described in Section 4.e of the Trust Legal Provisions and are provided without warranty as described in the Simplified BSD License.

## Table of Contents

1. The Internet-Standard Management Framework .....	3
2. Overview .....	3
2.1. The Proxy Mobile IPv6 Protocol Entities .....	3
2.2. Terminology .....	4
3. Proxy Mobile IPv6 Monitoring and Control Requirements .....	4
4. MIB Design .....	4
4.1. Textual Conventions .....	6
5. MIB Definitions .....	6
5.1. Proxy Mobile IPv6 Textual Conventions MIB .....	6
5.2. The Proxy Mobile IPv6 MIB .....	10
6. Security Considerations .....	58
7. IANA Considerations .....	60
8. References .....	60
8.1. Normative References .....	60
8.2. Informative References .....	61
9. Acknowledgements .....	62

## 1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP).

Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIV2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

## 2. Overview

### 2.1. The Proxy Mobile IPv6 Protocol Entities

Proxy Mobile IPv6 (PMIPv6) [RFC5213] is an extension to the Mobile IPv6 (MIPv6) protocol that facilitates network-based localized mobility management (NETLMM) for IPv6 nodes in a PMIPv6 domain. There are three types of entities envisaged by the PMIPv6 protocol.

mobile node (MN): In the PMIPv6 context, this term is used to refer to an IP host or router whose mobility is managed by the network.

local mobility anchor (LMA): Local Mobility Anchor is the home agent for the mobile node in a Proxy Mobile IPv6 domain. It is the topological anchor point for the mobile node's home network prefix(es) and is the entity that manages the mobile node's binding state. The local mobility anchor has the functional capabilities of a home agent as defined in the Mobile IPv6 base specification [RFC6275] with the additional capabilities required for supporting the Proxy Mobile IPv6 protocol as defined in the PMIPv6 specification [RFC5213].

mobile access gateway (MAG): Mobile Access Gateway is the entity on an access router that manages the mobility-related signaling for a mobile node that is attached to its access link. It is responsible for tracking the mobile node's movements to and from the access link and for signaling the mobile node's local mobility anchor.

This document defines a set of managed objects (MOs) that can be used to monitor and control PMIPv6 entities.

## 2.2. Terminology

The terminology used in this document is consistent with the definitions used in the Mobile IPv6 protocol specification [RFC6275] and in the NETLMM goals document [RFC4831].

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "NOT RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in BCP 14, RFC 2119 [RFC2119].

## 3. Proxy Mobile IPv6 Monitoring and Control Requirements

For managing a PMIPv6 entity, it is necessary to monitor the following:

- o capabilities of PMIPv6 entities
- o signaling traffic due to PMIPv6 signaling
- o binding-related details (at LMA and MAG)
- o binding-related statistics (at LMA and MAG)

## 4. MIB Design

The basic principle has been to keep the MIB as simple as possible and, at the same time, to make it effective enough so that the essential needs of monitoring and control are met.

The Proxy Mobile IPv6 Management Information Base (PMIPv6-MIB) extends the Mobile IPv6 Management Information Base (MIPv6-MIB) [RFC4295]. It is assumed that PMIPv6-MIB will always be implemented in conjunction with the MOBILEIPV6-MIB [RFC4295]. The PMIPv6-MIB uses the textual conventions defined in the INET-ADDRESS-MIB [RFC4001] and IP-MIB [RFC4293].

The PMIPv6-MIB is composed of the following groups of definitions:

- pmip6Core: a generic group containing objects that are common to all the Proxy Mobile IPv6 entities. Objects belonging to this group will be implemented on the corresponding Proxy Mobile IPv6 entity. pmip6BindingCacheTable belongs to this group.
- pmip6Mag: this group models the mobile access gateway service. Objects belonging to this group have the "pmip6Mag" prefix and will be implemented on the corresponding MAG.
- pmip6Lma: this group models the local mobility anchor service. Objects belonging to this group have the "pmip6Lma" prefix and will be implemented on the corresponding LMA.

- pmip6Notifications: defines the set of notifications that will be used to asynchronously monitor the Proxy Mobile IPv6 entities.

The tables contained in the above groups are as follows:

- pmip6BindingCacheTable: models the Binding Cache on the local mobility anchor.
- pmip6MagProxyCOATable: models the Proxy Care-of Addresses configured on the egress interfaces of the mobile access gateway.
- pmip6MagMnIdentifierTable: provides a mapping from the MAG-internal pmip6MagMnIndex to the mobile node identifier.
- pmip6MagMnLLIdentifierTable: provides a mapping from the MAG-internal pmip6MagMnLLIndex to the corresponding interface of the mobile node link-layer identifier.
- pmip6MagHomeNetworkPrefixTable: contains the home network prefixes assigned to interfaces of all mobile nodes attached to the MAG. Each interface is distinguished by the attached mobile node identifier (MN-Identifier) and the link-layer identifier (MN-LL-Identifier).
- pmip6MagBLTable: models the Binding Update List (BL) that includes PMIPv6-related information and is maintained by the mobile access gateway.
- pmip6MagMnProfileTable: contains the mobile node's policy profile that includes the essential operational parameters that are required by the network entities for managing the mobile node's mobility service.
- pmip6LmaLMAATable: contains the LMA Addresses (LMAAs) that are configured on the local mobility anchor. Each LMA Address acts as a transport endpoint of the tunnel between the local mobility anchor and the mobile access gateway.
- pmip6LmaMnIdentifierTable: provides a mapping from the LMA-internal pmip6BindingMnIndex to the mobile node identifier.
- pmip6LmaMnLLIdentifierTable: provides a mapping from the LMA-internal pmip6BindingMnLLIndex to the corresponding interface of the mobile node link-layer identifier.

- pmip6LmaHomeNetworkPrefixTable: contains the list of home network prefixes assigned to the connected interfaces of the mobile nodes anchored on an LMA.

#### 4.1. Textual Conventions

A Proxy Mobile IPv6 Textual Conventions MIB module containing Textual Conventions to represent commonly used Proxy Mobile IPv6 management information is defined. The intent is that these TEXTUAL CONVENTIONS (TCs) will be imported and used in PMIPv6-related MIB modules that would otherwise define their own representation(s). This MIB module includes references to RFC 4283 [RFC4283] and RFC 5213 [RFC5213].

### 5. MIB Definitions

#### 5.1. Proxy Mobile IPv6 Textual Conventions MIB

```

PMIPV6-TC-MIB DEFINITIONS ::= BEGIN
IMPORTS
    MODULE-IDENTITY, mib-2, Unsigned32
        FROM SNMPv2-SMI                -- [RFC2578]
    TEXTUAL-CONVENTION
        FROM SNMPv2-TC;                -- [RFC2579]

pmip6TCMIB MODULE-IDENTITY
    LAST-UPDATED "201205070000Z"      -- 7th May, 2012
    ORGANIZATION "IETF NETLMM Working Group"
    CONTACT-INFO
        "
            Glenn Mansfield Keeni
            Postal: Cyber Solutions, Inc.
                  6-6-3, Minami Yoshinari
                  Aoba-ku, Sendai, Japan 989-3204.
            Tel: +81-22-303-4012
            Fax: +81-22-303-4015
            EMail: glenn@cysols.com

            Sri Gundavelli
            Postal: Cisco Systems
                  170 W.Tasman Drive,
                  San Jose, CA 95134
                  USA
            Tel: +1-408-527-6109
            EMail: sgundave@cisco.com
        "

```

Kazuhide Koide  
 Postal: KDDI Corporation  
 GARDEN AIR TOWER 3-10-10, Iidabashi  
 Chiyoda-ku, Tokyo 102-8460, Japan.  
 Tel: +81-3-6678-3378  
 EMail: ka-koide@kddi.com

Ryuji Wakikawa  
 Postal: TOYOTA InfoTechnology Center, U.S.A., Inc.  
 465 Bernardo Avenue  
 Mountain View, CA  
 94043  
 USA  
 EMail: ryuji@us.toyota-itc.com  
 Support Group EMail: netlmm@ietf.org  
 "

## DESCRIPTION

"This MIB module provides textual conventions for Proxy Mobile IPv6 Management information.

Copyright (c) 2012 IETF Trust and the persons identified as authors of the code. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, is permitted pursuant to, and subject to the license terms contained in, the Simplified BSD License set forth in Section 4.c of the IETF Trust's Legal Provisions Relating to IETF Documents (<http://trustee.ietf.org/license-info>).

"

REVISION "201205070000Z" -- 7th May, 2012

## DESCRIPTION

"The initial version, published as RFC 6475."

::= { mib-2 205 }

-----  
 -- Textual Conventions  
 -----

Pmip6TimeStamp64 ::= TEXTUAL-CONVENTION

DISPLAY-HINT "6d:2d"

STATUS current

## DESCRIPTION

"A 64-bit unsigned integer field containing a timestamp. The value indicates the elapsed time since January 1, 1970, 00:00 UTC, by using a fixed-point format. In this

format, the integer number of seconds is contained in the first 48 bits of the field, and the remaining 16 bits indicate the number of 1/65536 fractions of a second.

"

REFERENCE

"RFC 5213: Section 8.8"

SYNTAX OCTET STRING (SIZE (8))

Pmip6MnIdentifier ::= TEXTUAL-CONVENTION

DISPLAY-HINT "255a"

STATUS current

DESCRIPTION

"The identity of a mobile node in the Proxy Mobile IPv6 domain. This is the stable identifier of a mobile node that the mobility entities in a Proxy Mobile IPv6 domain can always acquire and use for predictably identifying a mobile node. Various forms of identifiers can be used to identify a mobile node (MN). Two examples are a Network Access Identifier (NAI) and an opaque identifier applicable to a particular application.

"

REFERENCE

"RFC 4283: Section 3"

SYNTAX OCTET STRING (SIZE (0..255))

Pmip6MnLLIdentifier ::= TEXTUAL-CONVENTION

DISPLAY-HINT "255a"

STATUS current

DESCRIPTION

"An identifier that identifies the attached interface of a mobile node.

"

REFERENCE

"RFC 5213: Section 8.6"

SYNTAX OCTET STRING (SIZE (0..255))

Pmip6MnIndex ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d"

STATUS current

DESCRIPTION

"A unique integer value, greater than zero, assigned to each mobile node that is currently attached to the Proxy Mobile IPv6 domain by the management system. It is recommended that the values are assigned in a monotonically increasing order starting from 1. It may wrap after reaching its maximum value. The value for each mobile node must remain constant at least from one re-initialization of the entity's network management

```

        system to the next re-initialization.
    "
    SYNTAX          Unsigned32 (1..4294967295)
Pmip6MnLLIndex ::= TEXTUAL-CONVENTION
    DISPLAY-HINT "d"
    STATUS          current
    DESCRIPTION
        "A unique integer value, greater than zero, assigned to
        each interface of a mobile node that is currently
        attached to the Proxy Mobile IPv6 domain by the
        management system.
        It is recommended that the values are assigned in a
        monotonically increasing order starting from 1. It may
        wrap after reaching its maximum value. The value for
        each interface of a mobile node must remain constant at
        least from one re-initialization of the entity's network
        management system to the next re-initialization.
    "
    SYNTAX          Unsigned32 (1..4294967295)
Pmip6MnInterfaceATT ::= TEXTUAL-CONVENTION
    STATUS          current
    DESCRIPTION
        "The object specifies the access technology that
        connects the mobile node to the access link on the
        mobile access gateway.
        The enumerated values and the corresponding access
        technology are as follows:
            reserved                (0): Reserved (Not used)
            logicalNetworkInterface (1): Logical network interface
            pointToPointInterface  (2): Point-to-point interface
            ethernet                (3): Ethernet interface
            wirelessLan            (4): Wireless LAN interface
            wimax                  (5): Wimax interface
            threeGPPGERAN          (6): 3GPP GERAN
            threeGPPUTRAN          (7): 3GPP UTRAN
            threeGPPEUTRAN         (8): 3GPP E-UTRAN
            threeGPP2eHRPD         (9): 3GPP2 eHRPD
            threeGPP2HRPD          (10): 3GPP2 HRPD
            threeGPP21xRTT         (11): 3GPP2 1xRTT
            threeGPP2UMB           (12): 3GPP2 UMB
    "
    REFERENCE
        "RFC 5213: Section 8.5,
        Mobile IPv6 parameters registry on
        http://www.iana.org/mobility-parameters"

    SYNTAX INTEGER
    {

```

```

        reserved (0),
        logicalNetworkInterface(1),
        pointToPointInterface (2),
        ethernet (3),
        wirelessLan (4),
        wimax (5),
        threeGPPGERAN (6),
        threeGPPUTRAN (7),
        threeGPPEUTRAN (8),
        threeGPP2eHRPD (9),
        threeGPP2HRPD (10),
        threeGPP21xRTT (11),
        threeGPP2UMB (12)
    }
END

```

## 5.2. The Proxy Mobile IPv6 MIB

```

PMIPV6-MIB DEFINITIONS ::= BEGIN
IMPORTS
    MODULE-IDENTITY, mib-2, Integer32, Counter32, Gauge32,
    Unsigned32, OBJECT-TYPE, NOTIFICATION-TYPE
        FROM SNMPv2-SMI -- RFC 2578
    PhysAddress, TimeStamp,
    TruthValue
        FROM SNMPv2-TC -- RFC 2579
    MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP
        FROM SNMPv2-CONF -- RFC 2580
    InetAddressType, InetAddress, InetAddressPrefixLength
        FROM INET-ADDRESS-MIB -- RFC 4001
    Ipv6AddressIfIdentifierTC
        FROM IP-MIB -- RFC 4293
    mip6MnBLEntry, mip6BindingCacheEntry
        FROM MOBILEIPV6-MIB -- RFC 4295
    Pmip6TimeStamp64, Pmip6MnIdentifier,
    Pmip6MnLLIdentifier, Pmip6MnIndex, Pmip6MnLLIndex,
    Pmip6MnInterfaceATT
        FROM PMIPV6-TC-MIB -- RFC 6475
;

pmip6MIB MODULE-IDENTITY
    LAST-UPDATED "201205070000Z" -- 7th May, 2012
    ORGANIZATION "IETF NETLMM Working Group"
    CONTACT-INFO
        "
            Glenn Mansfield Keeni
            Postal: Cyber Solutions, Inc.
            6-6-3, Minami Yoshinari
            Aoba-ku, Sendai 989-3204, Japan.

```

Tel: +81-22-303-4012  
 Fax: +81-22-303-4015  
 EMail: glenn@cysols.com

Kazuhide Koide  
 Postal: KDDI Corporation  
 GARDEN AIR TOWER 3-10-10, Iidabashi  
 Chiyoda-ku, Tokyo 102-8460, Japan.  
 Tel: +81-3-6678-3378  
 EMail: ka-koide@kddi.com

Sri Gundavelli  
 Postal: Cisco  
 170 W.Tasman Drive,  
 San Jose, CA 95134  
 USA  
 Tel: +1-408-527-6109  
 EMail: sgundave@cisco.com

Ryuji Wakikawa  
 Postal: TOYOTA InfoTechnology Center, U.S.A., Inc.  
 465 Bernardo Avenue  
 Mountain View, CA  
 94043  
 USA  
 EMail: ryuji@us.toyota-itc.com

Support Group EMail: netlmm@ietf.org"

#### DESCRIPTION

"The MIB module for monitoring and controlling PMIPv6 entities.

Copyright (c) 2012 IETF Trust and the persons identified as authors of the code. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, is permitted pursuant to, and subject to the license terms contained in, the Simplified BSD License set forth in Section 4.c of the IETF Trust's Legal Provisions Relating to IETF Documents (<http://trustee.ietf.org/license-info>).

"

REVISION "201205070000Z" -- 7th May 2012  
 DESCRIPTION "Initial version, published as RFC 6475."  
 ::= { mib-2 206 }

-- The PMIPv6 MIB has the following 5 primary groups

```
pmip6Notifications    OBJECT IDENTIFIER ::= { pmip6MIB 0 }
pmip6Objects          OBJECT IDENTIFIER ::= { pmip6MIB 1 }
pmip6Conformance     OBJECT IDENTIFIER ::= { pmip6MIB 2 }
pmip6Core             OBJECT IDENTIFIER ::= { pmip6Objects 1 }
pmip6Mag              OBJECT IDENTIFIER ::= { pmip6Objects 2 }
pmip6Lma              OBJECT IDENTIFIER ::= { pmip6Objects 3 }
```

-- The sub groups

```
pmip6System           OBJECT IDENTIFIER ::= { pmip6Core 1 }
pmip6Bindings         OBJECT IDENTIFIER ::= { pmip6Core 2 }
pmip6Conf             OBJECT IDENTIFIER ::= { pmip6Core 3 }
pmip6Stats            OBJECT IDENTIFIER ::= { pmip6Core 4 }

pmip6MagSystem        OBJECT IDENTIFIER ::= { pmip6Mag 1 }
pmip6MagConf          OBJECT IDENTIFIER ::= { pmip6Mag 2 }
pmip6MagRegistration  OBJECT IDENTIFIER ::= { pmip6Mag 3 }

pmip6LmaSystem        OBJECT IDENTIFIER ::= { pmip6Lma 1 }
pmip6LmaConf          OBJECT IDENTIFIER ::= { pmip6Lma 2 }
```

-- The pmip6Stats group has the following sub groups

```
pmip6BindingRegCounters OBJECT IDENTIFIER ::= { pmip6Stats 1 }
```

--

--

-- pmip6System group

--

--

pmip6Capabilities OBJECT-TYPE

```
SYNTAX      BITS {
    mobilityAccessGateway (0),
    localMobilityAnchor   (1)
}
```

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object indicates the PMIPv6 functions that are supported by this managed entity. Multiple Proxy Mobile IPv6 functions may be supported by a single entity.  
mobilityAccessGateway(0) indicates the availability of the mobility access gateway function.  
localMobilityAnchor(1) indicates the availability of the local mobility anchor function."

```

"
REFERENCE
    "RFC 6275: Sections 3.2, 4.1"
 ::= { pmip6System 1 }

pmip6MobileNodeGeneratedTimestampInUse OBJECT-TYPE
    SYNTAX      TruthValue
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "This flag indicates whether or not the
        MN-generated timestamp mechanism is in use in that
        Proxy Mobile IPv6 domain.
        true(1) indicates that the local mobility anchors and
        mobile access gateways in that Proxy Mobile IPv6
        domain apply the MN-generated timestamp considerations.
        false(0) indicates that the MN-generated timestamp
        mechanism is not in use in that Proxy Mobile IPv6
        domain.
        The default value for this flag is 'false'."
"
REFERENCE
    "RFC 5213: Sections 5.5, 9.3"
    DEFVAL { false }
 ::= { pmip6Conf 1 }

pmip6FixedMagLinkLocalAddressOnAllAccessLinksType OBJECT-TYPE
    SYNTAX      InetAddressType
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "The InetAddressType of the
        pmip6FixedMagLinkLocalAddressOnAllAccessLinks
        that follows."
"
 ::= { pmip6Conf 2 }

pmip6FixedMagLinkLocalAddressOnAllAccessLinks OBJECT-TYPE
    SYNTAX      InetAddress
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "This variable indicates the link-local address value
        that all the mobile access gateways should use on
        any of the access links shared with any of the
        mobile nodes in that Proxy Mobile IPv6 domain.  If
        this variable is initialized with all zeroes, it
        implies that the use of fixed link-local address mode
        is not enabled for that Proxy Mobile IPv6 domain."

```

## REFERENCE

"RFC 5213: Sections 2.2, 6.8, 6.9.1.1, 6.9.3, 9.3"  
 ::= { pmip6Conf 3 }

pmip6FixedMagLinkLayerAddressOnAllAccessLinks OBJECT-TYPE

SYNTAX PhysAddress

MAX-ACCESS read-write

STATUS current

## DESCRIPTION

"This variable indicates the link-layer address value that all the mobile access gateways should use on any of the access links shared with any of the mobile nodes in that Proxy Mobile IPv6 domain. For access technologies where there is no link-layer address, this variable MUST be initialized with all zeroes."  
 "

## REFERENCE

"RFC 5213: Sections 6.9.3, 9.3"  
 ::= { pmip6Conf 4 }

pmip6MagStatus OBJECT-TYPE

SYNTAX INTEGER { enabled(1), disabled(2) }

MAX-ACCESS read-write

STATUS current

## DESCRIPTION

"This object indicates whether the PMIPv6 mobile access gateway function is enabled for the managed entity.

Changing the status from enabled(1) to disabled(2) will terminate the PMIPv6 mobile access gateway function. On the other hand, changing the status from disabled(2) to enabled(1) will start the PMIPv6 mobile access gateway function.

The value of this object MUST remain unchanged across reboots of the managed entity.  
 "

DEFVAL { disabled }

::= { pmip6MagSystem 1 }

pmip6MagProxyCOATable OBJECT-TYPE

SYNTAX SEQUENCE OF Pmip6MagProxyCOAEntry

MAX-ACCESS not-accessible

STATUS current

## DESCRIPTION

"This table models the Proxy Care-of Addresses configured on the egress interfaces of the mobile access gateway. This address is the transport endpoint of the

tunnel between the local mobility anchor and the mobile access gateway.

Entries in this table are not required to survive a reboot of the managed entity.

```

"
REFERENCE
  "RFC 5213: Sections 2.2, 6.10"
 ::= { pmip6MagSystem 2 }
pmip6MagProxyCOAEntry OBJECT-TYPE
  SYNTAX      Pmip6MagProxyCOAEntry
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "This entry represents a conceptual row in the
    Proxy-CoA table.  It represents a Proxy Care-of
    Address on the mobile access gateway.

    Implementers need to be aware that if the total
    number of octets in pmip6MagProxyCOA
    exceeds 113, then OIDs of column
    instances in this row will have more than 128
    sub-identifiers and cannot be accessed using
    SNMPv1, SNMPv2c, or SNMPv3."
  ::= { pmip6MagProxyCOAEntry 1 }
INDEX { pmip6MagProxyCOAEntry, pmip6MagProxyCOA }
 ::= { pmip6MagProxyCOAEntry 1 }

Pmip6MagProxyCOAEntry ::=
  SEQUENCE {
    pmip6MagProxyCOAEntryType  InetAddressType,
    pmip6MagProxyCOA           InetAddress,
    pmip6MagProxyCOAState     INTEGER
  }

pmip6MagProxyCOAEntryType OBJECT-TYPE
  SYNTAX      InetAddressType
  MAX-ACCESS  not-accessible
  STATUS      current
  DESCRIPTION
    "The InetAddressType of the pmip6MagProxyCOA
    that follows."
  ::= { pmip6MagProxyCOAEntry 1 }
pmip6MagProxyCOA OBJECT-TYPE
  SYNTAX      InetAddress
  MAX-ACCESS  not-accessible
  STATUS      current

```

## DESCRIPTION

"The Proxy-CoA configured on the egress interface of the mobile access gateway.

The type of the address represented by this object is specified by the corresponding pmip6MagProxyCOAType object.

## REFERENCE

"RFC 5213: Sections 2.2, 6.10"  
 ::= { pmip6MagProxyCOAEntry 2 }

pmip6MagProxyCOAState OBJECT-TYPE

SYNTAX INTEGER {  
                   unknown(1),  
                   activated(2),  
                   tunneled(3)  
 }

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object indicates the state of the Proxy-CoA:

unknown     -- The state of the Proxy-CoA cannot be determined.  
 activated    -- The Proxy-CoA is ready to establish a tunnel. This state SHOULD be indicated when the MAG is up but has no mobile node.  
 tunneled     -- Bidirectional tunnel is established using the Proxy-CoA.

::= { pmip6MagProxyCOAEntry 3 }

pmip6MagEnableMagLocalRouting OBJECT-TYPE

SYNTAX TruthValue

MAX-ACCESS read-write

STATUS current

## DESCRIPTION

"This flag indicates whether or not the mobile access gateway is allowed to enable local routing of the traffic exchanged between a visiting mobile node and a correspondent node that is locally connected to one of the interfaces of the mobile access gateway. The correspondent node can be another visiting mobile node as well, or a local fixed node.  
 true(1) indicates that the mobile access gateway routes the traffic locally.  
 false(0) indicates that the mobile access gateway reverse tunnels all the traffic to the mobile node's

local mobility anchor.

The default value for this flag is 'false'.

"

REFERENCE

"RFC 5213: Section 9.2" DEFVAL { false }  
 ::= { pmip6MagConf 1 }

pmip6MagMnIdentifierTable OBJECT-TYPE

SYNTAX SEQUENCE OF Pmip6MagMnIdentifierEntry  
 MAX-ACCESS not-accessible  
 STATUS current  
 DESCRIPTION

"A table containing the identifiers of mobile nodes attached to the MAG. Entries in this table are not required to survive a reboot of the managed entity.

"

REFERENCE

"RFC 5213: Sections 2.2, 6.1"  
 ::= { pmip6MagConf 2 }

pmip6MagMnIdentifierEntry OBJECT-TYPE

SYNTAX Pmip6MagMnIdentifierEntry  
 MAX-ACCESS not-accessible  
 STATUS current  
 DESCRIPTION

"An entry in the mobile node identifier table.

"

INDEX { pmip6MagBLMnIndex }  
 ::= { pmip6MagMnIdentifierTable 1 }

Pmip6MagMnIdentifierEntry ::=

SEQUENCE {  
 pmip6MagMnIdentifier Pmip6MnIdentifier  
 }

pmip6MagMnIdentifier OBJECT-TYPE

SYNTAX Pmip6MnIdentifier  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION

"The identity of a mobile node in the Proxy Mobile IPv6 domain.

"

REFERENCE

"RFC 5213: Sections 2.2, 6.1"

```

 ::= { pmip6MagMnIdentifierEntry 1 }

pmip6MagMnLLIdentifierTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Pmip6MagMnLLIdentifierEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "A table containing the link-layer identifiers
         of the interfaces of the mobile nodes attached
         to the MAG.
         Entries in this table are not required to survive
         a reboot of the managed entity.
        "
    REFERENCE
        "RFC 5213: Sections 2.2, 6.1"
 ::= { pmip6MagConf 3 }

pmip6MagMnLLIdentifierEntry OBJECT-TYPE
    SYNTAX      Pmip6MagMnLLIdentifierEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "An entry in the mobile node link-layer identifier
         table.
        "
    INDEX      { pmip6MagBLMnIndex, pmip6MagBLMnLLIndex
                }
 ::= { pmip6MagMnLLIdentifierTable 1 }

Pmip6MagMnLLIdentifierEntry ::=
    SEQUENCE {
        pmip6MagMnLLIdentifier      Pmip6MnLLIdentifier
    }

pmip6MagMnLLIdentifier OBJECT-TYPE
    SYNTAX      Pmip6MnLLIdentifier
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The link-layer identifier of the mobile node's
         connected interface on the access link.
        "
    REFERENCE
        "RFC 5213: Sections 2.2, 6.1"
 ::= { pmip6MagMnLLIdentifierEntry 1 }

pmip6MagHomeNetworkPrefixTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Pmip6MagHomeNetworkPrefixEntry

```

```

MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
    "A table representing the home network prefixes
    assigned to the connected interfaces of mobile nodes
    attached to the MAG.
    "
REFERENCE
    "RFC 5213: Sections 2, 6.1, 6.2"
 ::= { pmip6MagConf 4 }

pmip6MagHomeNetworkPrefixEntry OBJECT-TYPE
SYNTAX Pmip6MagHomeNetworkPrefixEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
    "An entry in the home network prefixes table.

    Implementers need to be aware that if the total
    number of octets in pmip6MagHomeNetworkPrefix
    exceeds 111, then OIDs of column instances in
    this row will have more than 128 sub-identifiers
    and cannot be accessed using SNMPv1, SNMPv2c, or
    SNMPv3.
    "
INDEX { pmip6MagBLMnIndex, pmip6MagBLMnLLIndex,
        pmip6MagHomeNetworkPrefixType,
        pmip6MagHomeNetworkPrefix }
 ::= { pmip6MagHomeNetworkPrefixTable 1 }

Pmip6MagHomeNetworkPrefixEntry ::=
SEQUENCE {
    pmip6MagHomeNetworkPrefixType      InetAddressType,
    pmip6MagHomeNetworkPrefix          InetAddress,
    pmip6MagHomeNetworkPrefixLength    InetAddressPrefixLength,
    pmip6MagHomeNetworkPrefixLifeTime  Unsigned32
}

pmip6MagHomeNetworkPrefixType OBJECT-TYPE
SYNTAX InetAddressType
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
    "The InetAddressType of the pmip6MagHomeNetworkPrefix
    that follows.
    "
 ::= { pmip6MagHomeNetworkPrefixEntry 1 }

```

```

pmip6MagHomeNetworkPrefix OBJECT-TYPE
    SYNTAX      InetAddress
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The mobile network prefix that is delegated to the
        mobile node. The type of the address represented by
        this object is specified by the corresponding
        pmip6MagHomeNetworkPrefixType object.
        "
    REFERENCE
        "RFC 5213: Section 2"
    ::= { pmip6MagHomeNetworkPrefixEntry 2 }

pmip6MagHomeNetworkPrefixLength OBJECT-TYPE
    SYNTAX      InetAddressPrefixLength
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The prefix length of the home network prefix.
        "
    ::= { pmip6MagHomeNetworkPrefixEntry 3 }

pmip6MagHomeNetworkPrefixLifeTime OBJECT-TYPE
    SYNTAX      Unsigned32
    UNITS       "seconds"
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The lifetime parameter (in seconds) that will be
        advertised in Router Advertisements by the MAG for
        this home network prefix.
        "
    REFERENCE
        "RFC 5213: Sections 6.2, 6.7"
    ::= { pmip6MagHomeNetworkPrefixEntry 4 }

pmip6MagBLTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Pmip6MagBLEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "This table corresponds to the Binding Update List (BL)
        that includes PMIPv6-related information and is
        maintained by the mobile access gateway.
        Entries from the table are deleted as the lifetime of
        the binding expires.
        "

```

```

REFERENCE
    "RFC 6275: Sections 4.5, 11.1
    RFC 5213: Section 6.1"
 ::= { pmip6MagRegistration 1 }
pmip6MagBLEntry OBJECT-TYPE
    SYNTAX      Pmip6MagBLEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "An entry containing additional information from
        a Binding Update sent by the mobile access gateway
        to the local mobility anchor.
        "
    AUGMENTS { mip6MnBLEntry }
 ::= { pmip6MagBLTable 1 }

Pmip6MagBLEntry ::= SEQUENCE {
    pmip6MagBLFlag          TruthValue,
    pmip6MagBLMnIndex      Pmip6MnIndex,
    pmip6MagBLMnLLIndex   Pmip6MnLLIndex,
    pmip6MagBLMagLinkLocalAddressType InetAddressType,
    pmip6MagBLMagLinkLocalAddress  InetAddress,
    pmip6MagBLMagIfIdentifierToMn   Ipv6AddressIfIdentifierTC,
    pmip6MagBLTunnelIfIdentifier    Ipv6AddressIfIdentifierTC,
    pmip6MagBLMnInterfaceATT        Pmip6MnInterfaceATT,
    pmip6MagBLTimeRecentlyAccepted  Pmip6TimeStamp64
}

pmip6MagBLFlag OBJECT-TYPE
    SYNTAX      TruthValue
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "true(1) indicates that the mobile access gateway sent
        the Proxy Binding Update with Proxy Registration Flag
        that indicates to the local mobility anchor that the
        registration is the Proxy Binding Update and is from a
        mobile access gateway.
        false(0) implies that the mobile access gateway is
        behaving as a simple mobile node.
        "
    REFERENCE
        "RFC 5213: Section 8.1"
 ::= { pmip6MagBLEntry 1 }

pmip6MagBLMnIndex OBJECT-TYPE
    SYNTAX      Pmip6MnIndex
    MAX-ACCESS  read-only

```

```

STATUS      current
DESCRIPTION
    "The index to the identifier of the attached mobile
    node in the pmip6MagMnIdentifierTable.
    "
REFERENCE
    "RFC 5213: Sections 2.2, 6.1, 8.1"
 ::= { pmip6MagBLEntry 2 }

```

```

pmip6MagBLMnLLIndex OBJECT-TYPE
SYNTAX      Pmip6MnLLIndex
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The index to the link-layer identifier of the mobile
    node's connected interface in the
    pmip6MagMnLLIdentifierTable.
    "
REFERENCE
    "RFC 5213: Sections 2.2, 6.1, 8.1"
 ::= { pmip6MagBLEntry 3 }

```

```

pmip6MagBLMagLinkLocalAddressType OBJECT-TYPE
SYNTAX      InetAddressType
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The InetAddressType of the pmip6MagBLMagLinkLocalAddress
    that follows.
    "
 ::= { pmip6MagBLEntry 4 }

```

```

pmip6MagBLMagLinkLocalAddress OBJECT-TYPE
SYNTAX      InetAddress
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The link-local address of the mobile access gateway on
    the access link shared with the mobile node.
    This is the address that is present in the Link-local
    Address option of the corresponding Proxy Binding Update
    message.
    "
REFERENCE
    "RFC 3963: Sections 4.1, 5.1"
 ::= { pmip6MagBLEntry 5 }

```

```

pmip6MagBLMagIfIdentifierToMn OBJECT-TYPE

```

```

SYNTAX      Ipv6AddressIfIdentifierTC
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The interface identifier (if-id) of the point-to-point
    link between the mobile node and the mobile access
    gateway. This is internal to the mobile access gateway
    and is used to associate the Proxy Mobile IPv6 tunnel
    to the access link where the mobile node is attached.
    "
REFERENCE
    "RFC 5213: Sections 6.1, 8.1"
 ::= { pmip6MagBLEntry 6 }

```

```

pmip6MagBLTunnelIfIdentifier OBJECT-TYPE
SYNTAX      Ipv6AddressIfIdentifierTC
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The tunnel interface identifier (tunnel-if-id) of the
    bidirectional tunnel between the mobile node's local
    mobility anchor and the mobile access gateway. This
    is internal to the mobile access gateway. The tunnel
    interface identifier is acquired during the tunnel
    creation.
    "
REFERENCE
    "RFC 5213: Sections 6.1, 8.1"
 ::= { pmip6MagBLEntry 7 }

```

```

pmip6MagBLMnInterfaceATT OBJECT-TYPE
SYNTAX      Pmip6MnInterfaceATT
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The type of the access technology by which the mobile
    node is currently attached to the mobile access gateway.
    "
REFERENCE
    "RFC 5213: Sections 6.9.1.1, 6.9.1.5, 8.1"
 ::= { pmip6MagBLEntry 8 }

```

```

pmip6MagBLTimeRecentlyAccepted OBJECT-TYPE
SYNTAX      Pmip6TimeStamp64
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "The 64-bit timestamp value of the most recently
    accepted Proxy Binding Update message sent for this

```

mobile node. This is the time of day on the mobile access gateway, when the Proxy Binding Acknowledgement message with the Status field set to 0 was received. If the Timestamp option is not present in the Proxy Binding Update message (i.e., when the sequence-number-based scheme is in use), the value MUST be initialized with all zeroes.

## REFERENCE

"RFC 5213: Sections 5.1, 8.1"  
 ::= { pmip6MagBLEntry 9 }

## pmip6MagMnProfileTable OBJECT-TYPE

SYNTAX SEQUENCE OF Pmip6MagMnProfileEntry  
 MAX-ACCESS not-accessible  
 STATUS current

## DESCRIPTION

"This table corresponds to the mobile node's policy profile that includes the essential operational parameters that are required by the network entities for managing the mobile node's mobility service. It contains policy profiles of mobile nodes that are connected to the mobile access gateway. Entries in this table are not required to survive a reboot of the managed entity."

## REFERENCE

"RFC 5213: Section 6.2"  
 ::= { pmip6MagRegistration 2 }

## pmip6MagMnProfileEntry OBJECT-TYPE

SYNTAX Pmip6MagMnProfileEntry  
 MAX-ACCESS not-accessible  
 STATUS current

## DESCRIPTION

"An entry containing information about the mobile node's policy profile."

INDEX { pmip6MagProfMnIndex }  
 ::= { pmip6MagMnProfileTable 1 }

## Pmip6MagMnProfileEntry ::=

SEQUENCE {  
 pmip6MagProfMnIndex Pmip6MnIndex,  
 pmip6MagProfMnIdentifier Pmip6MnIdentifier,  
 pmip6MagProfMnLocalMobilityAnchorAddressType  
 InetAddressType,  
 pmip6MagProfMnLocalMobilityAnchorAddress InetAddress

```

    }

pmip6MagProfMnIndex OBJECT-TYPE
    SYNTAX      Pmip6MnIndex
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "The index for a mobile node in the Proxy Mobile IPv6
        domain."
    ::= { pmip6MagMnProfileEntry 1 }

pmip6MagProfMnIdentifier OBJECT-TYPE
    SYNTAX      Pmip6MnIdentifier
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The identity of a mobile node in the Proxy Mobile IPv6
        domain."
    REFERENCE
        "RFC 5213: Section 2.2"
    ::= { pmip6MagMnProfileEntry 2 }

pmip6MagProfMnLocalMobilityAnchorAddressType OBJECT-TYPE
    SYNTAX      InetAddressType
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The InetAddressType of the
        pmip6MagMnLocalMobilityAnchorAddress that follows."
    ::= { pmip6MagMnProfileEntry 3 }
pmip6MagProfMnLocalMobilityAnchorAddress OBJECT-TYPE
    SYNTAX      InetAddress
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The global address that is configured on the interface
        of the local mobility anchor and is the transport
        endpoint of the bidirectional tunnel established
        between the local mobility anchor and the mobile access
        gateway. This is the address to which the mobile
        access gateway sends the Proxy Binding Update messages."
    REFERENCE
        "RFC 5213: Section 2.2"
    ::= { pmip6MagMnProfileEntry 4 }

```

```

pmip6BindingCacheTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Pmip6BindingCacheEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "This table models the Binding Cache on the local
        mobility anchor.

        Entries from the table are deleted as the lifetime
        of the binding expires.

        Entries in this table are not required to survive
        a reboot of the managed entity.
        "
    REFERENCE
        "RFC 6275: Sections 4.5, 9.1, 10.1
        RFC 5213: Section 5.1"
    ::= { pmip6Bindings 1 }

pmip6BindingCacheEntry OBJECT-TYPE
    SYNTAX      Pmip6BindingCacheEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "An entry containing additional information contained
        in the Binding Cache table of the local mobility anchor.
        "
    AUGMENTS { mip6BindingCacheEntry }
    ::= { pmip6BindingCacheTable 1 }

Pmip6BindingCacheEntry ::= SEQUENCE {
    pmip6BindingPBUFlag          TruthValue,
    pmip6BindingMnIndex          Pmip6MnIndex,
    pmip6BindingMnLLIndex        Pmip6MnLLIndex,
    pmip6BindingMagLinkLocalAddressType  InetAddressType,
    pmip6BindingMagLinkLocalAddress  InetAddress,
    pmip6BindingTunnelIfIdentifier  Ipv6AddressIfIdentifierTC,
    pmip6BindingMnInterfaceATT      Pmip6MnInterfaceATT,
    pmip6BindingTimeRecentlyAccepted  Pmip6TimeStamp64
}

pmip6BindingPBUFlag OBJECT-TYPE
    SYNTAX      TruthValue
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "true(1) indicates that the local mobility anchor

```

accepted the binding update with Proxy Registration Flag from a mobile access gateway.  
false(0) implies that the binding cache is from a mobile node. In this case, the remaining objects will not be accessible.

"

REFERENCE

"RFC 5213: Sections 5.1, 8.1"

::= { pmip6BindingCacheEntry 1 }

pmip6BindingMnIndex OBJECT-TYPE

SYNTAX Pmip6MnIndex

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"An index to the identifier of the registered mobile node.

"

REFERENCE

"RFC 5213: Sections 2.2, 5.1, 8.1

RFC 4283: Section 3"

::= { pmip6BindingCacheEntry 2 }

pmip6BindingMnLLIndex OBJECT-TYPE

SYNTAX Pmip6MnLLIndex

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The index to the link-layer identifier of the mobile node's connected interface on the access link.

"

REFERENCE

"RFC 5213: Sections 2.2, 5.1, 8.1"

::= { pmip6BindingCacheEntry 3 }

pmip6BindingMagLinkLocalAddressType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The InetAddressType of the pmip6BindingMagLinkLocalAddress that follows.

"

::= { pmip6BindingCacheEntry 4 }

pmip6BindingMagLinkLocalAddress OBJECT-TYPE

SYNTAX InetAddress

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"The link-local address of the mobile access gateway on the point-to-point link shared with the mobile node. This is generated by the local mobility anchor after accepting the initial Proxy Binding Update message. This is the address that is present in the Link-local Address option of the corresponding Proxy Binding Acknowledgement message.

"

## REFERENCE

"RFC 5213: Sections 5.1, 6.9.1.2, 8.2"  
 ::= { pmip6BindingCacheEntry 5 }

## pmip6BindingTunnelIfIdentifier OBJECT-TYPE

SYNTAX Ipv6AddressIfIdentifierTC  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"The tunnel interface identifier (tunnel-if-id) of the bidirectional tunnel between the local mobility anchor and the mobile access gateway where the mobile node is currently anchored. This is internal to the local mobility anchor. The tunnel interface identifier is acquired during the tunnel creation.

"

## REFERENCE

"RFC 5213: Sections 5.1, 8.1"  
 ::= { pmip6BindingCacheEntry 6 }

## pmip6BindingMnInterfaceATT OBJECT-TYPE

SYNTAX Pmip6MnInterfaceATT  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"The access technology type by which the mobile node is currently attached. This is obtained from the Access Technology Type option, present in the Proxy Binding Update message.

"

## REFERENCE

"RFC 5213: Sections 5.1, 8.1"  
 ::= { pmip6BindingCacheEntry 7 }

## pmip6BindingTimeRecentlyAccepted OBJECT-TYPE

SYNTAX Pmip6TimeStamp64  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"The 64-bit timestamp value of the most recently accepted Proxy Binding Update message sent for this mobile node. This is the time of day on the local mobility anchor, when the message was received. If the Timestamp option is not present in the Proxy Binding Update message (i.e., when the sequence number based scheme is in use), the value MUST be initialized with all zeroes.

"

REFERENCE

"RFC 5213: Sections 5.1, 8.1"  
 ::= { pmip6BindingCacheEntry 8 }

---

---

--- pmip6Stats group

---

---

--

-- pmip6Stats:pmip6BindingRegCounters

--

pmip6MissingMnIdentifierOption OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Missing mobile node identifier option' (Code 160).

Discontinuities in the value of this counter can occur at re-initialization of the mobile router, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"  
 ::= { pmip6BindingRegCounters 1 }

pmip6MagNotAuthorizedForProxyReg OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages

rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Not authorized to send Proxy Binding Updates' (Code 154).

Discontinuities in the value of this counter can occur at re-initialization of the mobile router, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"  
REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"  
 ::= { pmip6BindingRegCounters 2 }

pmip6NotLMAForThisMobileNode OBJECT-TYPE

SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Not local mobility anchor for this mobile node' (Code 153).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"  
REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"  
 ::= { pmip6BindingRegCounters 3 }

pmip6ProxyRegNotEnabled OBJECT-TYPE

SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Proxy Registration not enabled' (Code 152).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

## REFERENCE

"RFC 5213: Sections 5.3.1, 6.9.1.2, 8.9"

::= { pmip6BindingRegCounters 4 }

pmip6MissingHomeNetworkPrefixOption OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Missing home network prefix option' (Code 158). Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

## REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"

::= { pmip6BindingRegCounters 5 }

pmip6MissingHandOffIndicatorOption OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Missing handoff indicator option' (Code 161). Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

## REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"

::= { pmip6BindingRegCounters 6 }

pmip6MissingAccessTechTypeOption OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Missing access technology type option' (Code 162).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.3.1, 8.9"  
 ::= { pmip6BindingRegCounters 7 }

## pmip6NotAuthorizedForHomeNetworkPrefix OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Mobile node not authorized for one or more of the requesting home network prefixes' (Code 155).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.3.2, 6.9.1.2, 8.9"  
 ::= { pmip6BindingRegCounters 8 }

## pmip6TimestampMismatch OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'Invalid timestamp value (the clocks are out of sync)' (Code 156).

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.5, 6.9.1.2, 8.9"  
 ::= { pmip6BindingRegCounters 9 }

## pmip6TimestampLowerThanPrevAccepted OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'The timestamp value is lower than the previously accepted value' (Code 157). Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.5, 6.9.1.2, 8.9"  
 ::= { pmip6BindingRegCounters 10 }

## pmip6BcePbuPrefixSetDoNotMatch OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages rejected by the local mobility anchor with status code in the Binding Acknowledgement message indicating 'All the home network prefixes listed in the Binding Cache entry do not match all the prefixes in the received Proxy Binding Update' (Code 159). Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.4.1.1, 8.9"  
 ::= { pmip6BindingRegCounters 11 }

## pmip6InitialBindingRegistrations OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"Total number of Proxy Binding Update messages that newly creates the Binding Cache entry. Discontinuities in the value of this counter can occur at re-initialization of the management system,

and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

REFERENCE

"RFC 5213: Sections 5.3.2"  
 ::= { pmip6BindingRegCounters 12 }

pmip6BindingLifeTimeExtensionNoHandOff OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages for extending the binding lifetime, received from the same mobile access gateway that last updated the binding.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

REFERENCE

"RFC 5213: Sections 5.3.3"  
 ::= { pmip6BindingRegCounters 13 }

pmip6BindingLifeTimeExtensionAfterHandOff OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages for extending the binding lifetime, received from a new mobile access gateway where the mobile node's mobility session is handed off.

Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

"

REFERENCE

"RFC 5213: Sections 5.3.4"  
 ::= { pmip6BindingRegCounters 14 }

pmip6BindingDeRegistrations OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"Total number of Proxy Binding Update messages with the lifetime value of zero. Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.3.5"  
 ::= { pmip6BindingRegCounters 15 }

## pmip6BindingBindingAcks OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"Total number of Proxy Binding Acknowledgement messages. Discontinuities in the value of this counter can occur at re-initialization of the management system, and at other times as indicated by the value of pmip6CounterDiscontinuityTime.

## REFERENCE

"RFC 5213: Sections 5.3.5"  
 ::= { pmip6BindingRegCounters 16 }

## pmip6CounterDiscontinuityTime OBJECT-TYPE

SYNTAX TimeStamp  
 MAX-ACCESS read-only  
 STATUS current

## DESCRIPTION

"The value of sysUpTime on the most recent occasion at which any one or more of this PMIPv6 entity's global counters, viz., counters with OID prefix 'pmip6BindingRegCounters' suffered a discontinuity. If no such discontinuities have occurred since the last re-initialization of the local management subsystem, then this object will have a zero value.

::= { pmip6BindingRegCounters 17 }

## pmip6LmaStatus OBJECT-TYPE

SYNTAX INTEGER { enabled(1), disabled(2) }  
 MAX-ACCESS read-write  
 STATUS current

## DESCRIPTION

"This object indicates whether the PMIPv6 local

mobility anchor function is enabled for the managed entity.

Changing the status from enabled(1) to disabled(2) will terminate the PMIPv6 local mobility anchor function. On the other hand, changing the status from disabled(2) to enabled(1) will start the PMIPv6 local mobility anchor function.

The value of this object MUST remain unchanged across reboots of the managed entity.

```
"
DEFVAL { disabled }
::= { pmip6LmaSystem 1 }
```

pmip6LmaLMAAEntry OBJECT-TYPE

```
SYNTAX SEQUENCE OF Pmip6LmaLMAAEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
```

"This table models the LMA Addresses configured on the local mobility anchor. Each LMA Address acts as a transport endpoint of the tunnel between the local mobility anchor and the mobile access gateway and is the transport endpoint of the tunnel between the local mobility anchor and the mobile access gateway.

Entries in this table are not required to survive a reboot of the managed entity.

```
"
REFERENCE
"RFC 5213: Sections 2.2, 5.6"
::= { pmip6LmaSystem 2 }
```

pmip6LmaLMAAEntry OBJECT-TYPE

```
SYNTAX Pmip6LmaLMAAEntry
MAX-ACCESS not-accessible
STATUS current
DESCRIPTION
```

"This entry represents a conceptual row in the LMAA table. It represents each LMAA on the local mobility anchor.

Implementers need to be aware that if the total number of octets in pmip6LmaLMAA exceeds 113, then OIDs of column instances in this row will have more than 128 sub-identifiers and cannot be accessed using SNMPv1, SNMPv2c, or SNMPv3.

```

"
INDEX { pmip6LmaLMAAType, pmip6LmaLMAA }
 ::= { pmip6LmaLMAA 1 }

Pmip6LmaLMAAEntry ::=
SEQUENCE {
    pmip6LmaLMAAType      InetAddressType,
    pmip6LmaLMAA         InetAddress,
    pmip6LmaLMAAState    INTEGER
}

pmip6LmaLMAAType OBJECT-TYPE
SYNTAX      InetAddressType
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The InetAddressType of the pmip6LmaLMAA
    that follows."
 ::= { pmip6LmaLMAAEntry 1 }

pmip6LmaLMAA OBJECT-TYPE
SYNTAX      InetAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The LMAA configured on the local mobility anchor.

    The type of the address represented by this object
    is specified by the corresponding
    pmip6LmaLMAAType object."
REFERENCE
    "RFC 5213: Sections 2.2, 5.6"
 ::= { pmip6LmaLMAAEntry 2 }

pmip6LmaLMAAState OBJECT-TYPE
SYNTAX      INTEGER {
                                unknown(1),
                                activated(2),
                                tunneled(3)
                            }
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object indicates the state of the LMAA:
    unknown      -- The state of the LMAA
                  cannot be determined."

```

```

        activated    -- The LMAA is ready to establish
                       a tunnel.
        tunneled     -- The LMAA is used to set up the
                       bidirectional tunnel.
    "
 ::= { pmip6LmaLMAAEntry 3 }

pmip6LmaMinDelayBeforeBCEDelete OBJECT-TYPE
    SYNTAX      Integer32 (1..65535)
    UNITS       "milliseconds"
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "This variable specifies the length of time in
        milliseconds the local mobility anchor MUST wait before
        it deletes a Binding Cache entry of a mobile node, upon
        receiving a Proxy Binding Update message from a mobile
        access gateway with a lifetime value of 0.
        During this wait time, if the local mobility anchor
        receives a Proxy Binding Update for the same mobility
        binding, with a lifetime value greater than 0, then it
        must update the Binding Cache entry with the accepted
        binding values.  By the end of this wait time, if the
        local mobility anchor did not receive any valid Proxy
        Binding Update message for that mobility binding, it
        MUST delete the Binding Cache entry.  This delay
        essentially ensures that a mobile node's Binding Cache
        entry is not deleted too quickly and allows some time
        for the new mobile access gateway to complete the
        signaling for the mobile node.
        The default value for this variable is 10000
        milliseconds."
    "
    REFERENCE
        "RFC 5213: Sections 5.3.5, 9.1"
    DEFVAL { 10000 }
    ::= { pmip6LmaConf 1 }

pmip6LmaMaxDelayBeforeNewBCEAssign OBJECT-TYPE
    SYNTAX      Integer32 (1..65535)
    UNITS       "milliseconds"
    MAX-ACCESS  read-write
    STATUS      current
    DESCRIPTION
        "This variable specifies the length of time in
        milliseconds the local mobility anchor MUST wait for
        the de-registration message for an existing mobility
        session before it decides to create a new mobility

```

session.

The default value for this variable is 1500 milliseconds. Note that there is a dependency between this value and the values used in the retransmission algorithm for Proxy Binding Updates. The retransmissions need to happen before MaxDelayBeforeNewBCEAssign runs out, as otherwise there are situations where a de-registration from a previous mobile access gateway may be lost, and the local mobility anchor creates, needlessly, a new mobility session and new prefixes for the mobile node. However, this affects situations where there is no information from the lower layers about the type of a handoff or other parameters that can be used for identifying the mobility session.

"

REFERENCE

"RFC 5213: Sections 5.4.1.2, 5.4.1.3, 9.1"

DEFVAL { 1500 }  
 ::= { pmip6LmaConf 2 }

pmip6LmaTimestampValidityWindow OBJECT-TYPE

SYNTAX Integer32 (1..65535)

UNITS "milliseconds"

MAX-ACCESS read-write

STATUS current

DESCRIPTION

"This variable specifies the maximum length of time difference in milliseconds between the timestamp in the received Proxy Binding Update message and the current time of day on the local mobility anchor that is allowed by the local mobility anchor for the received message to be considered valid.  
 The default value for this variable is 300 milliseconds.  
 This variable must be adjusted to suit the deployments.

"

REFERENCE

"RFC 5213: Sections 5.5, 9.1"

DEFVAL { 300 }  
 ::= { pmip6LmaConf 3 }

pmip6LmaMnIdentifierTable OBJECT-TYPE

SYNTAX SEQUENCE OF Pmip6LmaMnIdentifierEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"A table containing the identifiers of mobile nodes served by the LMA.

Entries in this table are not required to survive a reboot of the managed entity.

"

REFERENCE

"RFC 5213: Sections 2, 6.1"

::= { pmip6LmaConf 4 }

pmip6LmaMnIdentifierEntry OBJECT-TYPE

SYNTAX Pmip6LmaMnIdentifierEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"An entry in the mobile node identifier table.

"

INDEX { pmip6BindingMnIndex  
}

::= { pmip6LmaMnIdentifierTable 1 }

Pmip6LmaMnIdentifierEntry ::=

SEQUENCE {

pmip6LmaMnIdentifier Pmip6MnIdentifier

}

pmip6LmaMnIdentifier OBJECT-TYPE

SYNTAX Pmip6MnIdentifier

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"The identity of a mobile node in the Proxy Mobile IPv6 domain.

"

REFERENCE

"RFC 5213: Section 2.2"

::= { pmip6LmaMnIdentifierEntry 1 }

pmip6LmaMnLLIdentifierTable OBJECT-TYPE

SYNTAX SEQUENCE OF Pmip6LmaMnLLIdentifierEntry

MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"A table containing the link-layer identifiers of the interfaces of the mobile nodes served by the LMA.

Entries in this table are not required to survive a reboot of the managed entity.

"

REFERENCE

"RFC 5213: Sections 2, 6.1"

```

 ::= { pmip6LmaConf 5 }

pmip6LmaMnLLIdentifierEntry OBJECT-TYPE
    SYNTAX      Pmip6LmaMnLLIdentifierEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "An entry in the mobile node link-layer identifier
        table."
    INDEX      { pmip6BindingMnIndex, pmip6BindingMnLLIndex }
 ::= { pmip6LmaMnLLIdentifierTable 1 }

Pmip6LmaMnLLIdentifierEntry ::=
    SEQUENCE {
        pmip6LmaMnLLIdentifier      Pmip6MnLLIdentifier
    }

pmip6LmaMnLLIdentifier OBJECT-TYPE
    SYNTAX      Pmip6MnLLIdentifier
    MAX-ACCESS  read-only
    STATUS      current
    DESCRIPTION
        "The link-layer identifier of the mobile node's
        connected interface on the access link."
 ::= { pmip6LmaMnLLIdentifierEntry 1 }

pmip6LmaHomeNetworkPrefixTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF Pmip6LmaHomeNetworkPrefixEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "A table representing the home network prefixes
        assigned to the connected interfaces of all the
        mobile nodes anchored at the LMA."
    REFERENCE
        "RFC 5213: Sections 2, 5.1, 5.2"
 ::= { pmip6LmaConf 6 }

pmip6LmaHomeNetworkPrefixEntry OBJECT-TYPE
    SYNTAX      Pmip6LmaHomeNetworkPrefixEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "An entry in the home network prefixes table."

```

Implementers need to be aware that if the total number of octets in pmip6LmaHomeNetworkPrefix exceeds 111 then OIDs of column instances in this row will have more than 128 sub-identifiers and cannot be accessed using SNMPv1, SNMPv2c, or SNMPv3.

```

"
INDEX { pmip6BindingMnIndex, pmip6BindingMnLLIndex,
        pmip6LmaHomeNetworkPrefixType,
        pmip6LmaHomeNetworkPrefix }
 ::= { pmip6LmaHomeNetworkPrefixTable 1 }

Pmip6LmaHomeNetworkPrefixEntry ::=
SEQUENCE {
    pmip6LmaHomeNetworkPrefixType      InetAddressType,
    pmip6LmaHomeNetworkPrefix          InetAddress,
    pmip6LmaHomeNetworkPrefixLength    InetAddressPrefixLength,
    pmip6LmaHomeNetworkPrefixLifeTime Gauge32
}

pmip6LmaHomeNetworkPrefixType OBJECT-TYPE
SYNTAX      InetAddressType
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The InetAddressType of the pmip6LmaHomeNetworkPrefix
    that follows."
 ::= { pmip6LmaHomeNetworkPrefixEntry 1 }

pmip6LmaHomeNetworkPrefix OBJECT-TYPE
SYNTAX      InetAddress
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "The mobile network prefix that is delegated to the
    mobile node. The type of the address represented by
    this object is specified by the corresponding
    pmip6LmaHomeNetworkPrefixType object."
REFERENCE
    "RFC 5213: Section 2"
 ::= { pmip6LmaHomeNetworkPrefixEntry 2 }

pmip6LmaHomeNetworkPrefixLength OBJECT-TYPE
SYNTAX      InetAddressPrefixLength
MAX-ACCESS  read-only

```

```

STATUS      current
DESCRIPTION
    "The prefix length of the home network prefix.
    "
 ::= { pmip6LmaHomeNetworkPrefixEntry 3 }

pmip6LmaHomeNetworkPrefixLifeTime OBJECT-TYPE
SYNTAX      Gauge32
UNITS       "seconds"
MAX-ACCESS  read-write
STATUS      current
DESCRIPTION
    "The lifetime (in seconds) granted to the mobile
    node for this registration.
    "
REFERENCE
    "RFC 5213: Section 5.3"
 ::= { pmip6LmaHomeNetworkPrefixEntry 4 }

--
-- pmip6Notifications
--
--

pmip6MagHomeTunnelEstablished NOTIFICATION-TYPE
OBJECTS     {
    pmip6MagBLTunnelIfIdentifier,
    pmip6MagProxyCOAState
}
STATUS      current
DESCRIPTION
    "This notification is sent by the Proxy Mobile IPv6
    entities every time the tunnel is established between
    the local mobility anchor and mobile access gateway.
    "
REFERENCE
    "RFC 5213: Section 5.6.1"
 ::= { pmip6Notifications 1 }

pmip6MagHomeTunnelReleased NOTIFICATION-TYPE
OBJECTS     {
    pmip6MagBLTunnelIfIdentifier,
    pmip6MagProxyCOAState
}
STATUS      current
DESCRIPTION
    "This notification is sent by the Proxy Mobile IPv6
    entities every time the tunnel between the local

```

```

        mobility anchor and mobile access gateway is released.
    "
REFERENCE
    "RFC 5213: Section 5.6.1"
    ::= { pmip6Notifications 2}

pmip6LmaHomeTunnelEstablished NOTIFICATION-TYPE
    OBJECTS      {
        pmip6BindingTunnelIfIdentifier,
        pmip6LmaLMAAState
    }
    STATUS      current
    DESCRIPTION
        "This notification is sent by the Proxy Mobile IPv6
        entities every time the tunnel is established between
        the local mobility anchor and mobile access gateway.
    "
REFERENCE
    "RFC 5213: Section 5.6.1"
    ::= { pmip6Notifications 3 }

pmip6LmaHomeTunnelReleased NOTIFICATION-TYPE
    OBJECTS      {
        pmip6BindingTunnelIfIdentifier,
        pmip6LmaLMAAState
    }
    STATUS      current
    DESCRIPTION
        "This notification is sent by the Proxy Mobile IPv6
        entities every time the tunnel between the local
        mobility anchor and mobile access gateway is released.
    "
REFERENCE
    "RFC 5213: Section 5.6.1"
    ::= { pmip6Notifications 4}

-- Conformance information
pmip6Groups      OBJECT IDENTIFIER ::= { pmip6Conformance 1 }
pmip6Compliances OBJECT IDENTIFIER ::= { pmip6Conformance 2 }

-- Units of conformance
pmip6SystemGroup OBJECT-GROUP
    OBJECTS      {
        pmip6Capabilities,
        pmip6MobileNodeGeneratedTimestampInUse,
        pmip6FixedMagLinkLocalAddressOnAllAccessLinksType,
        pmip6FixedMagLinkLocalAddressOnAllAccessLinks,
        pmip6FixedMagLinkLayerAddressOnAllAccessLinks
    }

```

```

}
STATUS current
DESCRIPTION
    " A collection of objects for basic PMIPv6
      monitoring."
 ::= { pmip6Groups 1 }

pmip6BindingCacheGroup    OBJECT-GROUP
OBJECTS {
    pmip6BindingPBUFlag,
    pmip6BindingMnIndex,
    pmip6BindingMnLLIndex,
    pmip6BindingMagLinkLocalAddressType,
    pmip6BindingMagLinkLocalAddress,
    pmip6BindingTunnelIfIdentifier,
    pmip6BindingMnInterfaceATT,
    pmip6BindingTimeRecentlyAccepted,
    pmip6LmaMnIdentifier,
    pmip6LmaMnLLIdentifier
}
STATUS current
DESCRIPTION
    " A collection of objects for monitoring the
      PMIPv6 extensions of the Binding Cache."
 ::= { pmip6Groups 2 }

pmip6StatsGroup          OBJECT-GROUP
OBJECTS {
    pmip6MissingMnIdentifierOption,
    pmip6MagNotAuthorizedForProxyReg,
    pmip6NotLMAForThisMobileNode,
    pmip6ProxyRegNotEnabled,
    pmip6MissingHomeNetworkPrefixOption,
    pmip6MissingHandOffIndicatorOption,
    pmip6MissingAccessTechTypeOption,
    pmip6NotAuthorizedForHomeNetworkPrefix,
    pmip6TimestampMismatch,
    pmip6TimestampLowerThanPrevAccepted,
    pmip6BcePbuPrefixSetDoNotMatch,
    pmip6InitialBindingRegistrations,
    pmip6BindingLifeTimeExtensionNoHandOff,
    pmip6BindingLifeTimeExtensionAfterHandOff,
    pmip6BindingDeRegistrations,
    pmip6BindingBindingAcks,
    pmip6CounterDiscontinuityTime
}
STATUS current
DESCRIPTION

```

```

        " A collection of objects for basic PMIPv6
        statistics monitoring.
        "
 ::= { pmip6Groups 3 }

pmip6MagSystemGroup      OBJECT-GROUP
  OBJECTS {
    pmip6MagStatus,
    pmip6MagProxyCOAState
  }
  STATUS current
  DESCRIPTION
    " A collection of objects for monitoring the
    PMIPv6-system-related objects on a mobile router."
 ::= { pmip6Groups 4 }

pmip6MagConfigurationGroup  OBJECT-GROUP
  OBJECTS {
    pmip6MagHomeNetworkPrefixLength,
    pmip6MagHomeNetworkPrefixLifeTime,
    pmip6MagEnableMagLocalRouting
  }
  STATUS current
  DESCRIPTION
    " A collection of objects for monitoring the
    configuration-related objects on a mobile access
    gateway.
    "
 ::= { pmip6Groups 5 }

pmip6MagRegistrationGroup  OBJECT-GROUP
  OBJECTS {
    pmip6MagBLFlag,
    pmip6MagBLMnIndex,
    pmip6MagBLMnLLIndex,
    pmip6MagBLMagLinkLocalAddressType,
    pmip6MagBLMagLinkLocalAddress,
    pmip6MagBLMagIfIdentifierToMn,
    pmip6MagBLTunnelIfIdentifier,
    pmip6MagBLMnInterfaceATT,
    pmip6MagBLTimeRecentlyAccepted,
    pmip6MagMnIdentifier,
    pmip6MagMnLLIdentifier,
    pmip6MagProfMnIdentifier,
    pmip6MagProfMnLocalMobilityAnchorAddressType,
    pmip6MagProfMnLocalMobilityAnchorAddress
  }
  STATUS current
  DESCRIPTION

```

```

    " A collection of objects for monitoring the
      registration-related objects on a mobile access
      gateway.
    "
 ::= { pmip6Groups 6 }

pmip6LmaSystemGroup      OBJECT-GROUP
OBJECTS {
    pmip6LmaStatus,
    pmip6LmaLMAAState
}
STATUS current
DESCRIPTION
    " A collection of objects for monitoring the
      system-related objects on an LMA."
 ::= { pmip6Groups 7 }

pmip6LmaConfigurationGroup  OBJECT-GROUP
OBJECTS {
    pmip6LmaMinDelayBeforeBCEDelete,
    pmip6LmaMaxDelayBeforeNewBCEAssign,
    pmip6LmaTimestampValidityWindow,
    pmip6LmaHomeNetworkPrefixLength,
    pmip6LmaHomeNetworkPrefixLifeTime
}
STATUS current
DESCRIPTION
    " A collection of objects for Monitoring the
      configuration-related objects on an LMA."
 ::= { pmip6Groups 8 }

pmip6MagNotificationGroup  NOTIFICATION-GROUP
NOTIFICATIONS {
    pmip6MagHomeTunnelEstablished,
    pmip6MagHomeTunnelReleased
}
STATUS current
DESCRIPTION
    "A collection of notifications from a home agent
      or correspondent node to the Manager about the
      tunnel status of the mobile router.
    "
 ::= { pmip6Groups 9 }

pmip6LmaNotificationGroup  NOTIFICATION-GROUP
NOTIFICATIONS {
    pmip6LmaHomeTunnelEstablished,
    pmip6LmaHomeTunnelReleased
}

```

```

}
STATUS current
DESCRIPTION
    "A collection of notifications from a home agent
    or correspondent node to the Manager about the
    tunnel status of the mobile router.
    "
 ::= { pmip6Groups 10 }

-- Compliance statements
pmip6CoreCompliance MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPv6-MIB.
    There are a number of INDEX objects that cannot be
    represented in the form of OBJECT clauses in
    SMIV2, but for which there are compliance
    requirements, expressed in OBJECT clause form in
    this description:
    -- OBJECT      pmip6BindingHomeAddressType
    -- SYNTAX      InetAddressType { ipv6(2) }
    -- DESCRIPTION
    -- This MIB module requires support for global
    -- ipv6 addresses for the pmip6BindingHomeAddress
    -- object.
    --
    "
MODULE -- this module
MANDATORY-GROUPS { pmip6SystemGroup
}
 ::= { pmip6Compliances 1 }

pmip6Compliance2 MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPv6-MIB.
    "
MODULE -- this module
MANDATORY-GROUPS { pmip6SystemGroup,
                    pmip6BindingCacheGroup,
                    pmip6StatsGroup
}
 ::= { pmip6Compliances 2 }

pmip6CoreReadOnlyCompliance MODULE-COMPLIANCE
STATUS current

```

```

DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPV6-MIB without support
    for read-write (i.e., in read-only mode).
    "
MODULE -- this module
    MANDATORY-GROUPS { pmip6SystemGroup
    }
OBJECT pmip6MobileNodeGeneratedTimestampInUse
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLocalAddressOnAllAccessLinksType
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLocalAddressOnAllAccessLinks
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLayerAddressOnAllAccessLinks
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."

 ::= { pmip6Compliances 3 }

pmip6ReadOnlyCompliance2 MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPV6-MIB without support
    for read-write (i.e., in read-only mode).
    "
MODULE -- this module
    MANDATORY-GROUPS { pmip6SystemGroup,
    pmip6BindingCacheGroup,
    pmip6StatsGroup
    }
OBJECT pmip6MobileNodeGeneratedTimestampInUse
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLocalAddressOnAllAccessLinksType
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLocalAddressOnAllAccessLinks

```

```

MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6FixedMagLinkLayerAddressOnAllAccessLinks
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."

 ::= { pmip6Compliances 4 }

pmip6MagCoreCompliance MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPV6-MIB.

    There are a number of INDEX objects that cannot be
    represented in the form of OBJECT clauses in
    SMIV2, but for which there are compliance
    requirements, expressed in OBJECT clause form in
    this description:
    -- OBJECT      pmip6MagProxyCOAType
    -- SYNTAX      InetAddressType { ipv6(2) }
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6MagProxyCOAType
    --      object.
    --
    -- OBJECT      pmip6MagProxyCOA
    -- SYNTAX      InetAddress (SIZE(16))
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6MagProxyCOA
    --      object.
    --
    "
MODULE -- this module
MANDATORY-GROUPS { pmip6MagSystemGroup
                   }
 ::= { pmip6Compliances 5 }

pmip6MagCompliance2 MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities that
    implement the PMIPV6-MIB for monitoring configuration-
    related information, registration details, and
    statistics on a mobile access gateway.

```

There are a number of INDEX objects that cannot be represented in the form of OBJECT clauses in SMIV2, but for which there are compliance requirements, expressed in OBJECT clause form in this description:

```

-- OBJECT      pmip6MagProxyCOAType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOA
--      object.
--
-- OBJECT      pmip6MagProxyCOA
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOAType
--      object.
--
-- OBJECT      pmip6MagHomeNetworkPrefixType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6MagHomeNetworkPrefix object.
--
-- OBJECT      pmip6MagHomeNetworkPrefix
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6MagHomeNetworkPrefix object.
--
"
MODULE -- this module
  MANDATORY-GROUPS { pmip6MagSystemGroup,
                     pmip6MagConfigurationGroup,
                     pmip6MagRegistrationGroup
                   }
 ::= { pmip6Compliances 6 }

pmip6MagCoreReadOnlyCompliance MODULE-COMPLIANCE
  STATUS current
  DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPV6-MIB without support
    for read-write (i.e., in read-only mode).

```

There are a number of INDEX objects that cannot be represented in the form of OBJECT clauses in SMIV2, but for which there are compliance requirements, expressed in OBJECT clause form in this description:

```
-- OBJECT      pmip6MagProxyCOAType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOA
--      object.
--
-- OBJECT      pmip6MagProxyCOA
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOAType
--      object.
--
-- OBJECT      pmip6MagHomeNetworkPrefixType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6MagHomeNetworkPrefix object.
--
```

"

```
MODULE -- this module
  MANDATORY-GROUPS { pmip6MagSystemGroup
  }
  OBJECT pmip6MagStatus
  MIN-ACCESS read-only
  DESCRIPTION
    "Write access is not required."
  ::= { pmip6Compliances 7 }
```

pmip6MagReadOnlyCompliance2 MODULE-COMPLIANCE

```
STATUS current
DESCRIPTION
```

"The compliance statement for SNMP entities that implement the PMIPV6-MIB without support for read-write (i.e., in read-only mode) and with support for monitoring configuration-related information, registration details, and statistics on a mobile access gateway.

There are a number of INDEX objects that cannot be represented in the form of OBJECT clauses in

SMIv2, but for which there are compliance requirements, expressed in OBJECT clause form in this description:

```

-- OBJECT      pmip6MagProxyCOAType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOA
--      object.
--
-- OBJECT      pmip6MagProxyCOA
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6MagProxyCOAType
--      object.
--
-- OBJECT      pmip6MagHomeNetworkPrefixType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6MagHomeNetworkPrefix object.
--
-- OBJECT      pmip6MagHomeNetworkPrefix
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6MagHomeNetworkPrefix object.
--
"
MODULE -- this module
    MANDATORY-GROUPS { pmip6MagSystemGroup,
                        pmip6MagConfigurationGroup,
                        pmip6MagRegistrationGroup
    }
    OBJECT pmip6MagStatus
    MIN-ACCESS read-only
    DESCRIPTION
        "Write access is not required."
    OBJECT pmip6MagEnableMagLocalRouting
    MIN-ACCESS read-only
    DESCRIPTION
        "Write access is not required."

 ::= { pmip6Compliances 8 }

```

```

pmip6LmaCoreCompliance MODULE-COMPLIANCE
  STATUS current
  DESCRIPTION
    "The compliance statement for SNMP entities
    that implement the PMIPV6-MIB.
    There are a number of INDEX objects that cannot be
    represented in the form of OBJECT clauses in
    SMIV2, but for which there are compliance
    requirements, expressed in OBJECT clause form in
    this description:
    -- OBJECT      pmip6LmaLMAAType
    -- SYNTAX      InetAddressType { ipv6(2) }
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6LmaLMAA
    --      object.
    --
    -- OBJECT      pmip6LmaLMAA
    -- SYNTAX      InetAddress (SIZE(16))
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6LmaLMAA
    --      object.
    --
    "
  MODULE -- this module
    MANDATORY-GROUPS { pmip6LmaSystemGroup
                       }
  ::= { pmip6Compliances 9 }

pmip6LmaCompliance2 MODULE-COMPLIANCE
  STATUS current
  DESCRIPTION
    "The compliance statement for SNMP entities that
    implement the PMIPV6-MIB for monitoring configuration-
    related information, registration details, and
    statistics on a mobile access gateway.

    There are a number of INDEX objects that cannot be
    represented in the form of OBJECT clauses in
    SMIV2, but for which there are compliance
    requirements, expressed in OBJECT clause form in
    this description:

    -- OBJECT      pmip6LmaLMAAType
    -- SYNTAX      InetAddressType { ipv6(2) }
    -- DESCRIPTION
    --      This MIB module requires support for global

```

```

--      IPv6 addresses for the pmip6LmaLMAA
--      object.
--
-- OBJECT      pmip6LmaLMAA
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6LmaLMAA
--      object.
--
-- OBJECT      pmip6LmaHomeNetworkPrefixType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6LmaHomeNetworkPrefix object.
--
-- OBJECT      pmip6LmaHomeNetworkPrefix
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6LmaHomeNetworkPrefix object.
--
"
MODULE -- this module
    MANDATORY-GROUPS { pmip6LmaSystemGroup,
                        pmip6LmaConfigurationGroup
                      }
 ::= { pmip6Compliances 10 }

pmip6LmaReadOnlyCompliance MODULE-COMPLIANCE
    STATUS current
    DESCRIPTION
        "The compliance statement for SNMP entities
        that implement the PMIPV6-MIB.
        There are a number of INDEX objects that cannot be
        represented in the form of OBJECT clauses in
        SMIV2, but for which there are compliance
        requirements, expressed in OBJECT clause form in
        this description:
        -- OBJECT      pmip6LmaLMAAType
        -- SYNTAX      InetAddressType { ipv6(2) }
        -- DESCRIPTION
        --      This MIB module requires support for global
        --      IPv6 addresses for the pmip6LmaLMAA
        --      object.
        --

```

```

-- OBJECT      pmip6LmaLMAA
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the pmip6LmaLMAA
--      object.
--
"
MODULE -- this module
  MANDATORY-GROUPS { pmip6LmaSystemGroup
                    }
  OBJECT pmip6LmaStatus
  MIN-ACCESS read-only
  DESCRIPTION
    "Write access is not required."
  ::= { pmip6Compliances 11 }

pmip6LmaReadOnlyCompliance2 MODULE-COMPLIANCE
  STATUS current
  DESCRIPTION
    "The compliance statement for SNMP entities that
    implement the PMIPV6-MIB without support
    for read-write (i.e., in read-only mode) and for
    monitoring configuration-related information,
    registration details, and statistics on a mobile
    access gateway.

    There are a number of INDEX objects that cannot be
    represented in the form of OBJECT clauses in
    SMIV2, but for which there are compliance
    requirements, expressed in OBJECT clause form in
    this description:

    -- OBJECT      pmip6LmaLMAAType
    -- SYNTAX      InetAddressType { ipv6(2) }
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6LmaLMAA
    --      object.

    --
    -- OBJECT      pmip6LmaLMAA
    -- SYNTAX      InetAddress (SIZE(16))
    -- DESCRIPTION
    --      This MIB module requires support for global
    --      IPv6 addresses for the pmip6LmaLMAA
    --      object.
    --

```

```

-- OBJECT      pmip6LmaHomeNetworkPrefixType
-- SYNTAX      InetAddressType { ipv6(2) }
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6LmaHomeNetworkPrefix object.
--
-- OBJECT      pmip6LmaHomeNetworkPrefix
-- SYNTAX      InetAddress (SIZE(16))
-- DESCRIPTION
--      This MIB module requires support for global
--      IPv6 addresses for the
--      pmip6LmaHomeNetworkPrefix object.
--
"
MODULE -- this module
    MANDATORY-GROUPS { pmip6LmaSystemGroup,
                        pmip6LmaConfigurationGroup
    }
OBJECT pmip6LmaStatus
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6LmaMinDelayBeforeBCEDelete
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6LmaMaxDelayBeforeNewBCEAssign
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6LmaTimestampValidityWindow
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."
OBJECT pmip6LmaHomeNetworkPrefixLifeTime
MIN-ACCESS read-only
DESCRIPTION
    "Write access is not required."

 ::= { pmip6Compliances 12 }

pmip6MagNotificationCompliance MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for SNMP entities that
    implement the PMIPV6-MIB and support notification
    from the mobile access gateway."

```

```

"
MODULE -- this module
  MANDATORY-GROUPS { pmip6MagNotificationGroup
                    }
 ::= { pmip6Compliances 13 }

pmip6LmaNotificationCompliance MODULE-COMPLIANCE
  STATUS current
  DESCRIPTION
    "The compliance statement for SNMP entities that
    implement the PMIPV6-MIB and support notification
    from the LMA.
    "
  MODULE -- this module
    MANDATORY-GROUPS { pmip6LmaNotificationGroup
                    }
 ::= { pmip6Compliances 14 }

END

```

## 6. Security Considerations

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and the corresponding sensitivity/vulnerability:

The value of the following objects is used to enable or disable the PMIPv6 functionality on the corresponding PMIPv6 entity. Access to these MOs may be abused to disrupt the communication that depends on the PMIPv6 functionality.

```

pmip6MagStatus
pmip6LmaStatus

```

Access to the following MOs may be abused to misconfigure PMIPv6 entities and disrupt communications.

```

pmip6MobileNodeGeneratedTimestampInUse
pmip6FixedMagLinkLocalAddressOnAllAccessLinksType
pmip6FixedMagLinkLocalAddressOnAllAccessLinks
pmip6FixedMagLinkLayerAddressOnAllAccessLinks
pmip6MagEnableMagLocalRouting
pmip6MagHomeNetworkPrefixLifeTime
pmip6LmaMinDelayBeforeBCEDelete
pmip6LmaMaxDelayBeforeNewBCEAssign
pmip6LmaTimestampValidityWindow

```

`pmip6LmaHomeNetworkPrefixLifeTime`

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

The following address-related objects may be considered to be particularly sensitive and/or private.

```
pmip6LmaHomeNetworkPrefixType
pmip6LmaHomeNetworkPrefix
pmip6LmaHomeNetworkPrefixLength
```

The following MN Identifier-related MOs may be used to identify users. These may be considered to be sensitive and/or private.

```
pmip6MagMnIdentifier
pmip6MagMnLLIdentifier
pmip6LmaMnIdentifier
pmip6LmaMnLLIdentifier
pmip6MagProfMnIdentifier
```

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPsec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Implementations MUST provide the security features described by the SNMPv3 framework (see [RFC3410]), including full support for authentication and privacy via the User-based Security Model (USM) [RFC3414] with the AES cipher algorithm [RFC3826]. Implementations MAY also provide support for the Transport Security Model (TSM) [RFC5591] in combination with a secure transport such as SSH [RFC5592] or TLS/DTLS [RFC6353].

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator

responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

## 7. IANA Considerations

IANA has assigned the following:

1. a base arc in the 'mib-2' (Standards Track) OID tree for the 'pmip6TCMIB' MODULE-IDENTITY defined in the PMIPV6-TC-MIB.
2. a base arc in the 'mib-2' (Standards Track) OID tree for the 'pmip6MIB' MODULE-IDENTITY defined in the PMIPV6-MIB.

## 8. References

### 8.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC2578] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April 1999.
- [RFC2579] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [RFC2580] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999.
- [RFC4001] Daniele, M., Haberman, B., Routhier, S., and J. Schoenwaelder, "Textual Conventions for Internet Network Addresses", RFC 4001, February 2005.
- [RFC4283] Patel, A., Leung, K., Khalil, M., Akhtar, H., and K. Chowdhury, "Mobile Node Identifier Option for Mobile IPv6 (MIPv6)", RFC 4283, November 2005.
- [RFC4293] Routhier, S., Ed., "Management Information Base for the Internet Protocol (IP)", RFC 4293, April 2006.
- [RFC4295] Keeni, G., Koide, K., Nagami, K., and S. Gundavelli, "Mobile IPv6 Management Information Base", RFC 4295, April 2006.

[RFC5213] Gundavelli, S., Ed., Leung, K., Devarapalli, V., Chowdhury, K., and B. Patil, "Proxy Mobile IPv6", RFC 5213, August 2008.

[RFC6275] Perkins, C., Ed., Johnson, D., and J. Arkko, "Mobility Support in IPv6", RFC 6275, July 2011.

## 8.2. Informative References

[RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", RFC 3410, December 2002.

[RFC3414] Blumenthal, U. and B. Wijnen, "User-based Security Model (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", STD 62, RFC 3414, December 2002.

[RFC3826] Blumenthal, U., Maino, F., and K. McCloghrie, "The Advanced Encryption Standard (AES) Cipher Algorithm in the SNMP User-based Security Model", RFC 3826, June 2004.

[RFC4831] Kempf, J., Ed., "Goals for Network-Based Localized Mobility Management (NETLMM)", RFC 4831, April 2007.

[RFC5591] Harrington, D. and W. Hardaker, "Transport Security Model for the Simple Network Management Protocol (SNMP)", RFC 5591, June 2009.

[RFC5592] Harrington, D., Salowey, J., and W. Hardaker, "Secure Shell Transport Model for the Simple Network Management Protocol (SNMP)", RFC 5592, June 2009.

[RFC6353] Hardaker, W., "Transport Layer Security (TLS) Transport Model for the Simple Network Management Protocol (SNMP)", RFC 6353, July 2011.

## 9. Acknowledgements

The following individuals and groups have contributed to this document with discussions and comments:

Adrian Farrel  
Dan Romascanu  
David Harrington  
Dirk von-Hugo  
Francis Dupont  
Harrie Hazewinkel  
Jari Arkko  
Sean Turner  
Stephen Farrell  
Vincent Roca  
WIDE Project netman-WG

## Authors' Addresses

Glenn Mansfield Keeni  
Cyber Solutions, Inc.  
6-6-3 Minami Yoshinari  
Aoba-ku, Sendai 989-3204  
Japan

Phone: +81-22-303-4012  
EMail: glenn@cysols.com

Kazuhide Koide  
KDDI Corporation  
GARDEN AIR TOWER 3-10-10, Iidabashi  
Chiyoda-ku, Tokyo, 102-8460  
Japan

Phone: +81-3-6678-3378  
EMail: ka-koide@kddi.com

Sri Gundavelli  
Cisco Systems  
170 W.Tasman Drive,  
San Jose, CA 95134  
USA

Phone: +1-408-527-6109  
EMail: sgundave@cisco.com

Ryuji Wakikawa  
TOYOTA InfoTechnology Center, U.S.A., Inc.  
465 Bernardo Avenue  
Mountain View, CA 94043  
USA  
EMail: ryuji@us.toyota-itc.com

